

Setting up LDAP Authentication

LDAP Authentication is accessible by administrator in **Settings > Authentication Provider > Ldap** tab in **Admin Area**.

Settings

- Check **Enable LDAP Authentication** checkbox.
(make sure that `$conf['auth_remote']` in the file `admin/config.inc.php` is set to 1)
- **LDAP Authentication**. To enable LDAP authentication check **Enable LDAP Authentication**
Make sure that the config variable `$conf['auth_remote']` in the file `admin/config.inc.php` is set to 1;
You can disable LDAP authentication by setting `$conf['auth_remote'] = 0`.
- **LDAP Options**. Identify host name of your LDAP server and the port for the protocols. The default port for LDAP over SSL is 636, for LDAP over TCP, UDP, or for TLS it is 389. You can specify Base DN for LDAP server and user DN and password. Leave **User DN** and **Password** fields empty for anonymous binding.

In order to use nested groups in Active Directory, you should set the LDAP membership attribute to `member:1.2.840.113556.1.4.1941:`
This is a special rule to perform a recursive group search.

For more information, see the following:
[https://msdn.microsoft.com/en-us/library/aa746475\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/aa746475(v=vs.85).aspx)
<https://blogs.technet.microsoft.com/...explore-group-membership-with-powershell/>
- **Configuration**. Set up the IP addresses for local authentication, specify whether to rewrite user data on login in **'Rewrite user on login'** field: 0 - once user created the data in KB will never be updated; 1 - on every authentication request, the user data in KB will be rewritten. You also can set up the options for updating user profiles and resetting password.
- **Group Mapping**. Here you can set up LDAP group mapping behavior. LDAP groups can be either static or dynamic. A static group entry contains a list of its users. A dynamic group is where the user entry contains a list of groups it belongs to.
- **User Mapping Fields**. Define the LDAP attributes - first name, last name, email, remote user id and attributes for privileges and roles (optional). In your expression use the round bracket to identify the specific characters to parse out the records as the field.
For user's privilege and role mapping you can give users privileges based upon their group attributes. Click [...] button to map LDAP groups to KBPublisher Privileges and/or Roles.

Please note, if you set mapping LDAP groups to the KBPublisher privileges, all matched users will be assigned the specified privilege. In case you do not have an Unlimited license, the number of allowed admin users could be exceeded and privilege will not be assigned to user.

Important! If you leave this field blank, roles and privileges assigned for users in KBPublisher will not be updated upon login.
- **Test / Debug Options (optional)**. Set up data to test / debug authentication for actual LDAP user.

Tip: You can disable LDAP authentication by setting `$conf['auth_remote'] = 0`; in file `/kbp_dir/admin/config.inc.php`

Article ID: 371

Last updated: 9 Oct, 2017

Updated by: Leontev E.

Revision: 7

KBPublisher 8.0 Knowledge Management Handbook -> Single Sign On -> LDAP Authentication -> Setting up LDAP Authentication

<https://www.kbpublisher.com/kb/entry/371/>